

The Art Sexy Lightbox is an extension for the Joomla CMS created by Artetics. The extension allows you to show photos and photo groups, Flicker photos, Picasa and Photobucket albums, image galleries, external pages and inline content in a customizable modal window.

To begin using the Art Sexy Lightbox extension on your Joomla 3 installation follow three simple steps below.

## Step 1

The Art Sexy Lightbox extension comes with a plugin and module. You will need to install both the plugin and module from your Joomla 3 backend by visiting **Extensions > Extension Manager > Install > Upload Package File**. We recommend installing the plugin first.



**Note:** After installation enable the Art Sexy Lightbox plugin from the Joomla Plugin Manager.

## Step 2

Now that you've installed and enabled the Art Sexy Lightbox plugin, you'll need to configure the settings. Open the plugin to set the following settings: Show duration, Close duration, Move duration, Resize duration, Thumbnail width, Thumbnail height

and Flickr API key.

Show duration	200
Close duration	400
Move duration	800
Resize duration	800
Thumbnail width	
Thumbnail height	
Flickr API Key	

**Note:** You must have a Flickr API key to display images from your Flickr account.

# Artetics

## **Getting started with the Art Sexy Lightbox**

The following plugin settings are available to customize the Art Sexy Lightbox:

- •Show Duration the amount of time the lightbox will show the default is 200 milliseconds.
- •Close Duration the amount of time the lighbox will close the default is 400 milliseconds.
- •Move Duration the amount of time the lightbox will move the default is 800 milliseconds.
- •Resize Duration the amount of time the lightbox will resize the default is 800 milliseconds.
- •Thumbnail Width this is the width of the small lightbox image.
- •Thumbnail Height this is the height of the small lightbox image.
- •Flickr API Key this is a key provided by Flickr.

## Step 3

Now that you've installed the Art Sexy Lightbox extension and setup the plugin parameters, now you're ready to setup the module. The module allows you to place an image gallery in a module position.

To setup the module, go to the module manager in your Joomla 3 installation and locate the Art Sexy Lightbox module. If it's not installed, you will need to install a new module and set the status to **Published**.



Now go to the **Module** tab.



In the Art Sexy Lightbox module tab we'll discuss the following sections:


- 1. Common Options set the type of gallery to show in the moduel and common options.
- 2. Thumbnail Options set the thumbnail options for the gallery selected in the module.
- 3. Local Images Options show images from a local folder on a server.
- 4. Flickr Feed show images from a Flickr photo feed.
- 5. Flickr Photo Set show images from a Flickr photo set.
- 6. Picasa Album show images from a Picasa album.
- 7. Photobucket Album show images from a Photobucket album.
- 8. Inline Content show any HTML in a lightbox.
- 9. Images From External Server show images from an external server.
- 10. News and Articles in a Lightbox show Joomla article in a lightbox.
- 11. External Page show external pages and articles in a lightbox.
- 12. Module show images in a module position.

**Note:** You can leave the module title as the default name or rename it.



## **Common Options**


The following are the Art Sexy Lightbox common options that can be configured in the module:





#### **Thumbnail Options**

The following are the Art Sexy Lightbox thumbnail options that can be configured in the module:





## **Local Images Options**

The following are the Art Sexy Lightbox local images options that can be configured in the module:

Local images options				
Path to images folder			Set the path to the images folder.	
Path to thumbnail folder			Set the path to the thumbnail folder.	
Path to folder with large image			Set the path to the folder with the larger image:	
lmage captions				
			Set the image captions.	
Sallery type	Simple gallery		Set the gallery type.	
Show single image or text	Show full gallery	•	Set to show single image or text.	
Single image or text			Indicate random to show random imag	
Show single image	yes		Set to show single image or from folde	
Sortimages	ascending		Set alt tags for images.	
Carousel		j	Sort images; ascending, etc.	
/isible items in carousel	5		Set number of visible items in carouse	
Scroll items in carousel	1			
Cloud carousel			Set number of scroll items in carousel	
Container height	500px		Set container height and width.	
( position	285			
/ position	120		Set module x and y position and y radius.	
/ Radius	40			
Reflection height	58		Set reflection height.	
fide buttons	no	*	Set yes or no to hide button.	
otate delay	2500		Set rotate delay in milliseconds.	
uto rotate	yes		Set yes or no to auto rotate images	



## **Third Party Image Providers**


The following are the Art Sexy Lightbox Flickr feed, Flickr photo set, Picasa album and Photobucket album settings that can be configured in the module:

2. Flickr feed		
Flickr user name		Input your Flickr username.
Image size	default	Set the image site or leave as default.
3. Flickr photo set		
Flickr user name		Input your Flickr username.
Flickr API Key		Input your Flickr API key.
Flickr photo set		Set your Flickr photo set
Thumbnail size	small (75x75)	Set the thumbnail size.
4. Picasa album		
Picasa user		Input your Picasa username.
Picasa album		Set your Picasa album.
Picasa thumbnail size	default	Set the Picasa thumbnail size.
Picasa image size	1280	Set the Picasa image size; default is 1280 pixels.
5. Photobucket album		
Photobucket URL		Input your Photobucket URL.



#### **Inline Content**

The following are the Art Sexy Lightbox inline content settings that can be configured in the module:



#### **Images From External Server**


The following are the Art Sexy Lightbox images from external server settings that can be configured in the module:

"	7. Images from external server		1 [	exte	rnal server; format should be o://server/images/imglist.php
	Remote server link		Not	te:	This requires imglist.php from the installation archive to be placed in the images folder on the external server.




## **News and Articles In a Lightbox**

The following are the Art Sexy Lightbox news and articles in a lightbox settings that can be configured in the module:




#### **External Page**

The following are the Art Sexy external page settings that can be configured in the module:



#### Module

The following are the Art Sexy external page settings that can be configured in the module:






#### Plugin User Case - News and Articles in a Lightbox

There are a variety of ways you can use the Art Sexy Lightbox plugin. In the following example, we'll show you how to use the News and Articles option in a lightbox.

**Note:** To use the Art Sexy Lightbox plugin, you must insert the plugin code into an article. Good practice is to insert the plugin code in plain text mode since some WYSIWYG editors can place inappropriate characters in the content.

#### **Backend Article Manager**

Create or open an article and paste the code. Then set the code parameters. For example you can change the "previewWidth="700" to "500".



#### **Frontend Article**



## Module User Case - News and Articles in a Lightbox

The Art Sexy Lightbox module has a variety of options to select from to place an image gallery in a module position.


**Note:** To use the News and Articles in a lightbox module option, you have to create a Joomla article and category.

#### **Backend Module Manager**

First set the common options to show News and articles in a lightbox.



Then set your **News and articles in a lightbox** settings.





Module User Case - News and Articles in a Lightbox

#### **Frontend View**

Here is how your **News and articles in a lightbox** will appear in modal on the frontend.

